

Barnes & Noble Press Quick Guide: Book Interior File Preparation

| | Settings | | | | How To | |
|------------|--|----|----|-----------------|---|---|
| | Size | PB | HC | HC w/ Jacket | | |
| Trim Size | 4" x 6" | × | | | <p>Traditional sizes for fiction or narrative non-fiction books are: 4" x 6" (Popular Mass Market size); 4.25" x 7" (Popular Mass Market size); 4.37" x 7" (Popular Mass Market size); 5" x 8"; 5.06" x 7.81"; 5.83" x 8.27" (Popular UK size); 5.25" x 8"; 5.5" x 8.25"; 5.5" x 8.5"; 6"x9"; 6.14" x 9.21"</p> <p>Traditional sizes for cookbooks or other designed books are: 7" x 10"; 7.5" x 9.25"; 8" x 10"; 8.25" x 11"; 8.268" x 11.693" (Popular UK size); 8.5" x 8.5"; 8.5" x 11"</p> <p>Traditional size for children's books is: 11" x 8.5"; 8.25" x 11"; 8.268" x 11.693" (Popular UK size)</p> | |
| | 4.25" x 7" | × | | | | |
| | 4.37" x 7" | × | | | | |
| | 5" x 8" | × | × | × | | |
| | 5.06" x 7.81" | × | | | | |
| | 5.25" x 8" | × | | | | |
| | 5.5" x 8.25" | × | | | | |
| | 5.5" x 8.5" | × | × | × | | |
| | 5.83" x 8.27" | × | × | | | |
| | 6" x 9" | × | × | × | | |
| | 6.14" x 9.21" | × | × | × | | |
| | 7" x 10" | × | × | | | |
| | 7.44" x 9.69" | × | | | | |
| | 7.5" x 9.25" | × | × | | | |
| | 8" x 8" | × | × | | | |
| | 8" x 10" | × | × | | | |
| | 8.25" x 11" | × | | | | |
| | 8.268" x 11.693" | × | | | | |
| | 8.5" x 8.5" | × | × | | | |
| 8.5" x 11" | × | × | | | | |
| 11" x 8.5" | × | × | | | | |
| Margins | Top: 0.5" Outside: 0.5" Bottom: 0.5" Inside: 0.75" Gutter: 0.0" Mirror Margins: Yes | | | | PC | From the Page Layout Tab - Choose: 1. Margins (icon) 2. Custom Margins (at the bottom of the list) 3. Enter in the margin and gutter settings (displayed to the left) 4. Check the checkbox to enable mirror margins |
| | | | | | Mac | From the Page Layout Tab - Choose: 1. Margins (icon) 2. Custom Margins (at the bottom of the list) 3. Enter in the margin and gutter settings (displayed to the left) 4. Check the checkbox to enable mirror margins |

Barnes & Noble Press Quick Guide: Book Interior File Preparation

| | Settings | How To | |
|-------------|--|--------|--|
| Page Size | Set page size to the trim size you want (e.g. 6" x 9") | PC | From the Page Layout Tab - Choose: 1. Size (icon) 2. More Paper Sizes (opens Page Set Up Dialog Box) 3. From the Page Set Up Dialog box you can adjust the paper size |
| | | Mac | From the File Menu - Choose: 1. Page Set Up 2. On the Page Set Up Dialog box click on Paper Size and choose Manage Custom Sizes 3. Add the appropriate paper width and height for your trim size |
| Embed Fonts | Fonts must be embedded | PC | Go to the Office button in the upper left corner 1. In the bottom right of that screen choose Word Options 2. In the left menu choose Save 3. In the last section of that dialog box under Preserve Fidelity, check the embed font checkbox |
| | | Mac | Fonts automatically embed |
| Images | Must be 300 DPI or Higher | | |
| Save as PDF | | PC | From the Office button 1. Select Save As 2. Select Adobe PDF 3. Click on Options, then check the box ISO 19005-1 Compliant PDF / A |
| | | Mac | From the File menu 1. Select Save As 2. Select PDF from the Format drop down menu |